



Wisconsin Web Offset step by step guide on how-to prepare a spot color Photoshop file.

This is quick guide to achieving proper spot color separations from a Adobe Photoshop file.

Step 1. Covert file to Grayscale (or Bitmap)



Step 2.Duplicate Channel



for additional technical support or questions contact Kim Tuyls (kim.tuyls@wwoffset.com)

21045 Enterprise Avenue • Brookfield, WI 53045 262•395•2008 toll-free 877•201•6809

www.wwoffset.com – [ftp.wwoffset.com](ftp://www.wwoffset.com)

Spot Color from a Photoshop File

Step 3. Erase everything you **do not** want to be spot for the duplicate channel (Gray Copy) or copy image into new spot channel and erase anything you **do not** want to be spot.




Erase or delete everything you **do not** want to be the spot color.

or...

copy image into new spot channel and erase anything you **do not** want to be spot.

Step 4. Choose Color for New Spot Channel or choose Channel Options.



Choose color in New Spot Channel

or

Channel Options

Select Spot Color

Solidity 100% from Channel options.


for additional technical support or questions contact Kim Tuyls (kim.tuyls@wwoffset.com)

21045 Enterprise Avenue • Brookfield, WI 53045 262•395•2008 toll-free 877•201•6809


www.wwoffset.com – [ftp.wwoffset.com](ftp://www.wwoffset.com)

Spot Color from a Photoshop File

Step 5. Either from the New Spot Channel or Channel Options choose a Pantone Color




Step 6. Choose Image -> Mode -> Multichannel



for additional technical support or questions contact Kim Tuyls (kim.tuyls@wwoffset.com)
21045 Enterprise Avenue • Brookfield, WI 53045 262•395•2008 toll-free 877•201•6809
www.wwoffset.com – [ftp.wwoffset.com](ftp://www.wwoffset.com)

Spot Color from a Photoshop File

Step 7. Save as Photoshop DCS 2.0 (save as .eps file)



Step 8. Place .eps file in InDesign and use separation preview.



for additional technical support or questions contact Kim Tuyls (kim.tuyls@wwoffset.com)

21045 Enterprise Avenue • Brookfield, WI 53045 262•395•2008 toll-free 877•201•6809

www.wwoffset.com – ftp.wwoffset.com